

LiveScan3D manual (a work in progress)

LiveScan3D is a software designed for real time 3D reconstruction using multiple Kinect v2 depth sensors simultaneously at real time speed. The produced 3D reconstruction is in the form of a coloured point cloud, with points from all of the Kinects placed in the same coordinate system. Possible use scenarios of the system include:

- capturing an object's 3D structure from multiple viewpoints simultaneously - Figure 1,
- capturing "panoramic" 3D structure of a scene – Figure 2,
- increasing the density of a point cloud captured by a single sensor, by having multiple sensors capture the same scene.

At the moment connecting multiple Kinect v2 devices to a single computer is difficult and only possible under Linux.

Because of those limitations, in our system each Kinect v2 sensor is connected to a separate computer. Each of those computers is connected to a server which governs all of the sensors. The server allows the user to perform calibration, filtering, synchronized frame capture, and to visualize the acquired point cloud live. Sequence of clouds, captured in real-time, can be stored in .ply files



Figure 1: A setup for capturing an object from multiple viewpoints.



Figure 2: A setup for capturing a panoramic 3D reconstruction.

Step by step configuration (Tutorial 1)

In this tutorial we describe step by step how to configure and run LiveScan3D with Kinect v2 sensors in a scenario where all Kinects are able to see a single calibration marker. In order to start you will need to:

- have at least one Kinect v2 sensor,
- download LiveScan3D from <http://ztv.ire.pw.edu.pl/mkowalski/> where it is available as a compiled binary or compile it yourself from source code available on GitHub <http://github.com/MarekKowalski/LiveScan3D/>
- download and install the Kinect for Windows SDK 2.0 on each machine you intend to use as a client,
- download and install the Visual C++ Redistributable for Visual Studio 2013,

- have all of the computers you will use in the same network,
- print the calibration pattern “calibration0.jpg” on a piece of paper (A4 size should be enough).

Once you have all of the preliminary steps completed, run the LiveScanClient application on each of your client computers. If everything is working fine, you should see the RGB camera stream of your Kinect inside the application window.

Next, choose a computer that will act as a server (this computer may also be a client at the same time), we recommend that it is the most powerful of the available machines. Run the LiveScanServer on the chosen machine and click “Start server” to begin listening for client connections. Connect each of the clients to the server. If the client is running on the same machine as the server, there is no need for inputting an IP address (it defaults to 127.0.0.1).

At this point your server window should show some clients connected. You can press “show live” to see the output from the sensors. Here you will notice two things, first of all the point clouds from different devices are not aligned, second of all the frame rate might be low. The first problem arises, because the clients are not “calibrated”. By calibration here I mean “knowing the location of the Kinect sensor in the scene”. As for the low FPS in the live view window, please read the section of the manual about this window.

In order to calibrate the clients you need the printed calibration pattern. Once printed, attach it to something rigid and place it in a position where it is visible to all sensors. Note that the calibration pattern (marker) must be visible to the sensor’s depth and color stream, you can check if it is by pressing “show depth” in the client window.

Now there is only one last thing you need to do, which is to make sure that the server knows which marker you want to use. In order to make sure that is the case go to settings and make sure that under “calibration markers” you have a marker with id 0. Now all you have to do is press calibrate and the data from your Kinects should align. You can check if that is the case in the live view window.

If there is a demand I will keep extending this manual to different scenarios such as “what if I want to place many Kinects in a configuration where not every sensor can see that one single marker”.

LiveScanServer

The LiveScanServer application governs the clients and allows for calibration, filtering, sequence recording, live preview of the reconstruction etc. Below you will find a separate section for each window of LiveScanServer with explanations of each of the program's functionalities.

Main window




Figure 3: The main window of the server application. It shows two clients connected, one of which is calibrated.

1. Starts and stops the server – the server needs to be started before any work can be done. If there are any errors when trying to start, make sure that this is the only instance of LiveScanServer running and that there are no apps using port 48001.
2. Opens the settings window – more details below.
3. Performs calibration using markers – each client performs the calibration separately and once it succeeds that client show “Calibrated = true”. In order to perform calibration the clients need to know the locations of the markers in the scene, those locations are set in the settings menu. If a client sees many markers, the largest one is always used.

In some scenes where not all Kinects are able to see the same marker, you will need to use more than one. There are six different marker patterns included in the project files. Each of them corresponds to a unique id of 0 to 5. In order to use a marker with a given id it needs to be added to the set of known markers in the settings window.

If one of the clients does not calibrate, there can be several reasons:

- The marker is not getting detected – this is fairly common if there are bad light conditions. Try and move it around, or switch the light on in the room to see if it helps.
- The marker's pose is not known to the client – this usually manifests by a green border around the marker (which indicates that it is correctly detected), but no calibration. To fix this, simply add the marker with the proper id in the settings menu.

4. Refines the current calibration – if all of the sensors are already calibrated and there still some misalignment between the point clouds, this functionality may help. It uses Iterative Closest Points (ICP) to refine the alignment between the point clouds. This function only works well if there is a fair deal of common surfaces between the point clouds from different sensors. You can use it multiple times for further improvement.
5. Performs recording – once this button is pressed the clients begin to capture and locally store frames in a synchronous manner. Once you press this button again, the recording will stop and the clients will begin uploading the frames to the server. The server will save them as PLY files in a directory specified by “sequence name”. Pressing the button again before all frames are saved will stop saving and allow the recording of a new sequence.
6. Opens the live view window – more details below.
7. Sequence name – this specifies the directory to which the PLY files will be saved if you perform recording. The whole directory path will be “./out/<sequence name>”.
8. List of all of the connected clients – it shows the client IP addresses along with the information on whether they are properly calibrated or not.

Setting window




Figure 4: The settings window of the server application. Two markers are defined.

Expect more details here soon.

Live view window




Figure 5: The live view window, the number of frames per second (FPS) is visible in the window's title.

This window shows the reconstructed point cloud from all of the sensors. Apart from the points themselves you will also find the marker positions in the scene as red lines and sensor positions as green lines. The frame rate here depends greatly on the speed of your network and on the number of devices you are using. In the future (hopefully near future), we plan to work on reducing the size of the point clouds, which should increase the FPS.

Remember that even when there are only a few frames per second in this window, the frame rate should be high if you record the frames (using the "Start recording" button in LiveScanServer).

There is a number of ways to move around the reconstructed point cloud in this window:

- Left mouse button – lets you rotate the point cloud,
- Right mouse button – lets you move the camera,
- Mouse wheel – zoom in/zoom out,
- W, S, A, D keys – let you move the camera around like in an FPS game,
- +, - keys – change the size of the points.